



上海思响信息科技有限公司

地址：上海市浦东新区东方路428号235室

邮箱：yiwen.zhu@compuTherm.com

电话：13901652239

Pandat 软件

第一期优化培训教程

第三讲





2020年7月4日

CompuTherm, LLC
8401 Greenway Blvd, Middleton, WI, USA
<http://www.compuTherm.com>





答 疑

- 那个偏晶相图怎么计算，下次上课能展示一下吗？
- 下次上课时能否讲一下如何保存，调用和修改batch file？
- 能否讲一下如何进行high throughput计算
- 关于Pandat 的console module

偏晶相图vs吉布斯能



偏晶相图vs吉布斯能



HTC 计算

➤ **高通量计算:** 在多维成分空间内, 用户可以通过定义成分范围, 来进行成千上万的计算。

➤ **计算结果的数据挖掘:** 通过对计算结果进行数据挖掘, 确定满足用户定义的性能标准的合金成分范围。

➤ **目的:** 加速新合金设计与研发

	Start	End	# Steps
w%(Co)	0	30	10
w%(Cr)	20	50	10
w%(Cu)	0	10	5
w%(Fe)	10	20	5
w%(Li)	0	5	5
w%(Mg)	5	10	5
w%(Mn)	10	15	5
▶ w%(Ni)	-1	-1	-1
w%(Ti)	5	15	10

Solidification Model
☒ Non-equilibrium (Scheil) ☐ Equilibrium (Lever)

Start simulation from liquidus surface ☒
End when no more liquid ☒
T_End [C]: 0
Max Temperature Step Size [K]: 4

HTC 计算步骤

- 第一步: 用户定义成分
- 第二步: Pandat 进行所有成分的计算并且储存为一个工作空间。
- 第三步: 用户定义合金选择的标准条件
- 第四步: Pandat 在计算结果中进行数据挖掘, 确定符合用户标准的合金成分。
- 第五步: Pandat 软件将数据挖掘结果显示为表格, 并可利用表格数据绘制各种图形。


$$10 \times 10 \times 5 \times 5 \times 5 \times 5 \times 10 = 625000$$



Console 模块

C:\Program Files (x86)\CompuTherm LLC\Pandat 2020\Pandat 2020 Examples\ConsoleMode

Pandat Manual: Page 38



Name


- bin
- image
- Pandat 2020 Example book
- Pandat 2020 Examples
- pre-install
- Pandat License Agreement Install.rtf
- Readme.rtf

PanPy 模块: Pandat 与Python结合, 开源。
将在今年下半年的新版本中推出。

细说 TDB 文件

- Define **Elements** (and **Species**) in the system
- Define **Functions** (Gibbs energy functions at reference state)
- Define **Phases** (Sublattice Model, Site occupation, model parameters, Modification to normal state, such as Magnetic term, ordered part)

Element



```
Element CaO Halite 56.077 0 38.100 !
```



Note

- Pandat has a built-in table of atomic weights of elements.
- If a compound (e.g., Al_2O_3) is defined as an element, its atomic weight has to be specified in the definition.
- Pandat does not use structure, H_{298} and S_{298} in current version.


CaMgO_TEST.tdb CaO-MgO_Test.tdb



Species




Function



$$G_{Al}^{HCP} = 5481 - 1.8T + G_{Al}^{HSEr} (J/mol) \quad (298.15K \leq T \leq 6000K)$$




Function (multiple ranges)



$$\begin{aligned}
 G_{Al}^{HSE} &= -7976.15 + 137.072 T - 24.3672 T \ln(T) - 0.00188466 T^2 - 8.77664e-007 T^3 \\
 &\quad + 74092 T^{-1}; \quad (J/mol) \quad (298.15K \leq T \leq 700K) \\
 &= -11276.2 + 223.027 T - 38.5844 T \ln(T) + 0.018532 T^2 - 5.76423e-006 T^3 \\
 &\quad + 74092 T^{-1}; \quad (J/mol) \quad (700K \leq T \leq 933.6K) \\
 &= -11277.7 + 188.662 T - 31.7482 T \ln(T) - 1.23426e+028 T^{-9} \\
 &\quad (J/mol) \quad (933.6K \leq T \leq 2900K)
 \end{aligned}$$



Type Definition



f : antiferromagnetic factor: **-1** for Bcc; **-3** for Fcc and Hcp


p : the fraction of the magnetic enthalpy absorbed above the critical temperature, depends on the structure

p = 0.40 (Bcc)


p = 0.28 (Fcc, Hcp...)





Type Definition




Phase



Constituent



Parameter




$$x_{Al} G_{Al}^{Liquid,0}$$

where

$$G_{Al}^{Liquid,0} = GLIQA1 \quad (J/mol) \quad (298.15K \leq T \leq 3000K)$$



Parameter



$$x_{Al}x_{Zn}(x_{Al}-x_{Zn})^1 L_{Al,Zn}^{Liquid,1}$$

where

$$L_{Al,Zn}^{Liquid,1} = -810 + 0.471 \cdot T \text{ (J/mol)} \quad (298.15K \leq T \leq 6000K)$$



Parameter

Parameter G(Liquid,Al,Mg,Zn;0) 298.15 -4094.48; 6000 N !
Parameter G(Liquid,Al,Mg,Zn;1) 298.15 -39973.7; 6000 N !
Parameter G(Liquid,Al,Mg,Zn;2) 298.15 -11337.5; 6000 N !

$$x_{Al}x_{Mg}x_{Zn}\left(x_{Al}L_{Al,Mg,Zn}^{Liquid,0} + x_{Mg}L_{Al,Mg,Zn}^{Liquid,1} + x_{Zn}L_{Al,Mg,Zn}^{Liquid,2}\right)$$

where

$$\begin{aligned}L_{Al,Mg,Zn}^{Liquid,0} &= -4094.48 \quad (J/mol) \quad (298.15K \leq T \leq 6000K) \\L_{Al,Mg,Zn}^{Liquid,1} &= -39973.7 \quad (J/mol) \quad (298.15K \leq T \leq 6000K) \\L_{Al,Mg,Zn}^{Liquid,2} &= -11337.5 \quad (J/mol) \quad (298.15K \leq T \leq 6000K)\end{aligned}$$



Parameter

```
Phase BCC_A2 %c 1 1 !
Constituent BCC_A2 :Al,Mg,Zn:!
Parameter G(BCC_A2,Al;0) 298.15 +GBCCAl; 6000 N !
Parameter G(BCC_A2,Mg;0) 298.15 +3100-2.1*T+GHSERMg; 6000 N !
Parameter G(BCC_A2,Zn;0) 298.15 +GBCCZn; 6000 N !
Parameter G(BCC_A2,Al,Zn;0) 298.15 +20000; 6000 N !
```

$$G^{BCC_A2} = x_{Al}G_{Al}^{BCC_A2,0} + x_{Mg}G_{Mg}^{BCC_A2,0} + x_{Zn}G_{Zn}^{BCC_A2,0} \\ + RT(x_{Al}\ln x_{Al} + x_{Mg}\ln x_{Mg} + x_{Zn}\ln x_{Zn}) \\ + x_{Al}x_{Zn}L_{Al,Zn}^{BCC_A2,0}$$

where

$$\begin{aligned} G_{Al}^{BCC_A2,0} &= GBCCAl & (J/mol) & (298.15K \leq T \leq 6000K) \\ G_{Mg}^{BCC_A2,0} &= 3100-2.1*T+GHSERMg & (J/mol) & (298.15K \leq T \leq 6000K) \\ G_{Zn}^{BCC_A2,0} &= GBCCZn & (J/mol) & (298.15K \leq T \leq 6000K) \\ L_{Al,Zn}^{BCC_A2,0} &= 20000 & (J/mol) & (298.15K \leq T \leq 6000K) \end{aligned}$$

Parameter

```
Phase SIGMA % 2 0.66667 0.33333 !
Constituent SIGMA : Al,Zn : Mg : !
Parameter G(SIGMA,Al:Mg;0) 298.15 +20133.7+6.3946*T
+0.66667*GLIQAl+0.33333*GLIQMg; +3000 N !
Parameter G(SIGMA,Zn:Mg;0) 298.15 -19389.7+13.644*T
+0.66667*GLIQZn+0.33333*GLIQMg; 3000 N !
Parameter G(SIGMA,Al,Zn:Mg;0) 298.15 -26000; 3000 N !
Parameter G(SIGMA,Al,Zn:Mg;1) 298.15 +9335.47; 3000 N !
```


$$G^{\sigma} = y_{Al}^1 y_{Mg}^2 G_{Al:Mg}^{\sigma,0} + y_{Zn}^1 y_{Mg}^2 G_{Zn:Mg}^{\sigma,0} \\ + RT[a^1(y_{Al}^1 \ln y_{Al}^1 + y_{Zn}^1 \ln y_{Zn}^1) + a^2(y_{Mg}^2 \ln y_{Mg}^2)] \\ + y_{Al}^1 y_{Zn}^1 y_{Mg}^2 L_{Al,Zn:Mg}^{\sigma,0} + y_{Al}^1 y_{Zn}^1 y_{Mg}^2 (y_{Al}^1 - y_{Zn}^1) L_{Al,Zn:Mg}^{\sigma,1}$$

where

$$G_{Al:Mg}^{\sigma,0} = 20133.7 + 6.3946 \cdot T + 0.66667 \cdot GLIQAl + 0.33333 \cdot GLIQMg \\ G_{Zn:Mg}^{\sigma,0} = -19389.7 + 13.644 \cdot T + 0.66667 \cdot GLIQZn + 0.33333 \cdot GLIQMg \\ L_{Al,Zn:Mg}^{\sigma,0} = -26000 \\ L_{Al,Zn:Mg}^{\sigma,1} = 9335.47 \\ a^1 = 0.66667 \\ a^2 = 0.33333$$



Parameter to be optimized







Note

- Parameters to be optimized are defined in the TDB file.
- Good start values for parameters are needed for efficient optimization.
- The lower bound and upper bound need to be selected carefully.



优化前的准备

-  理论信息 (Theoretical information)
-  实验数据 (Experimental data)
-  估算数据 (Estimated data)
-  类似体系 (Assessments of similar system)



实验数据

- 晶体结构

根据晶体结构选择合适的模型

- 物理性质(磁性, 摩尔体积)

- 热力学性质数据

液相: 比热, 混合焓, 活度, 蒸汽压 等

固相: 比热, 形成焓, 电动势, 分解压 等

- 相平衡数据: 实验相图

相图边界, 相区等。

热力学数据

- 量热数据(Calorimetric data): **Enthalpy** of mixing, ~ of formation, ~ of transformation
- 电动势(EMF), Knudsen cell data: 化学势, 活度
- 相分压(partial pressure): 活度
- DSC: 比热, **Enthalpy** of transformation (相变热, 相变焓)



相平衡数据

- DTA/DSC: start/end temperatures of transformations
- Microscope(OM,SEM, TEM): phase identification, determining phase amounts
- EPMA (EDX) : phase identification, phase compositions (tie-lines)
- XRD: phase identification, lattice parameters.
- Neutron diffraction: site occupancies

估计数据与第一原理计算数据

Miedema 模型

Enthalpy of mixing

第一原理计算

Enthalpy of formation at 0 K


<https://materialsproject.org/>

<http://oqmd.org/>

Cp



相似合金体系



S.-M. Liang, R. Schmid-Fetzer, Evaluation of Calphad Approach and Empirical Rules on the Phase Stability of Multi-principal Element Alloys, J. Phase Equilib. Diffus., 38 (2017) 369-381.

数据的优先级别

实验数据 > 第一原理计算数据 > 估计数据

实验数据: 直接测定的实验数据,
而不是推导的实验数据

比如: 实验测得活度或者分压, 推导出混合焓,
只能用活度来进行优化, 而不能用它推导出的混合焓。

细说 pop 文件：实验数据文件

POP 文件: 储存用于优化的实验数据.

- 常用的关键词:
CREATE_NEW_EQUILIBRIUM,
SET_CONDITION,
EXPERIMENT
- Syntax 与 Thermocalc 一致.

Keywords required by a typical equilibrium

CREATE_NEW_EQUILIBRIUM @@, 1

CHANGE_STATUS PHASE FCC_A1#1, FCC_A1#2 = FIX 1


SET_CONDITION P = P0, T = 500

EXPERIMENT X(FCC_A1#1, AL) = 0.2 : DX1, X(FCC_A1#2, AL) = 0.8 : DX1

SET_START_VALUE Y(FCC_A1#1,AL) = 0.2

SET_START_VALUE Y(FCC_A1#2,AL) = 0.8

Define constant/function in pop file




Note

- These constants/functions may be used in the following part.



Define a table in pop file




Note

- Similar equilibria can be formulated as a table, such as two-phase equilibria at different temperatures in a binary system.
- Table values are listed as a matrix.
 - Each row represents the condition or properties for one equilibrium.
 - The columns are separated by space or tab, and expressed as @<column number>, i.e. @1, @2, @3 and so on.



Define an equilibrium in pop file




Note

- The reaction identifier number can be a natural number or “@@”. “@@” means the number increased by 1 from the previous equilibrium.
- The initialization code can be 0, 1 or 2.
 - 1: all components are entered but all phases are suspended. it is appropriate in most cases.
 - 0: all components and phases are suspended.
 - 2: all components and phases are initially entered.



Define an equilibrium in pop file




Note

- Phases name:
 - * means all the phases.
 - #1 and #2 postfixes are used for a phase with miscibility gap.
- Phase status:
 - S : phase suspended, not considered in the equilibrium.
 - FIX: phase used as fixed, must involves in the equilibrium.
 - ENT: phase used as entered, involves in the equilibrium.
 - DORM: phase used as dormant, not involves in the equilibrium, used to calculate the driving force for this phase.



Define an equilibrium in pop file




Note

- Keyword **SET_CONDITION** is used to input the given condition about an equilibrium, such as pressure (in Pa), temperature (in K) and alloy compositions (in atomic/weight fraction).
- The property value can be a real number, a defined constant, or the values of a specific column in a table.



Define an equilibrium in pop file




Note

- Keyword **EXPERIMENT** is only used in pop file for fine-tune. It is used to input all the information about an equilibrium under given conditions, such as temperature (in K), phase compositions, activity and other properties.
- The property value can be a real number, a defined constant, or the values of a specific column in a table.
- The error bar can be a real number, a defined constant, the values of a specific column in a table, or a relevant percentage of the property value.



Set reference state for an element




Note

- Keyword **SET_REFERENCE_STATE** is used to set the element reference state when calculating relative properties, such as enthalpy, activity.




Set start values



Note

- Keyword **SET_START_VALUE** is used to give some good starting point for the optimizer to calculate the equilibrium locally.
- The property value can be a real number, a defined constant, the values of a specific column in a table, or even an expression.

End of the pop file




Note

- Keyword **SAVE_WORKSPACES** is required for the end of inputting equilibria into the pop file.



Al-Zn 相图实验数据: 相边界



Two-phase equilibria example

\$ Tieline between FCC_A1#1 and FCC_A1#2

TABLE_HEAD

CREATE_NEW_EQUILIBRIUM @@, 1

CHANGE_STATUS PHASE * = S

CHANGE_STATUS PHASE FCC_A1#1, FCC_A1#2 = FIX 1

SET_CONDITION P = P0, T = @1

EXPERIMENT X(FCC_A1#1, AL) = @3 : DX1, X(FCC_A1#2, AL) = @2 : DX1

SET_START_VALUE Y(FCC_A1#1, AL) = @3

SET_START_VALUE Y(FCC_A1#2, AL) = @2

TABLE_VALUES

\$ LIST THE PHASE COMPOSITION IN EQUILIBRIUM

\$ T[K] X(FCC_A1#2, AL) X(FCC_A1#1, AL)

552	0.86	0.41
570	0.83	0.445
599	0.78	0.52
622	0.67	0.64

TABLE_END



Three-phase equilibrium example

\$ Invariant Reaction: LIQUID => FCC_A1 + HCP_A3

CREATE_NEW_EQUILIBRIUM @@, 1

CHANGE_STATUS PHASE LIQUID, FCC_A1, HCP_A3 = FIX 1

SET_CONDITION P = P0

EXPERIMENT T = 655 : DT2

EXPERIMENT X(LIQUID,ZN) = 0.89 : DX2


EXPERIMENT X(FCC_A1,ZN) = 0.667 : DX2

EXPERIMENT X(HCP_A3,ZN) = 0.977 : DX2

SET_START_VALUE T = 648



Al-Zn 相图实验数据: 液相混合焓



Enthalpy of mixing example

\$ Enthalpy of mixing for liquid phase at 953K

TABLE_HEAD

CREATE_NEW_EQUILIBRIUM @@,1

CHANGE_STATUS PHASE * = S

CHANGE_STATUS PHASE LIQUID = FIX 1

SET_CONDITION T = 953, P = P0, X(LIQUID,ZN) = @1

EXPERIMENT HMR(LIQUID) = @3 : @4

SET_REFERENCE_STATE AL LIQUID * 1E5

SET_REFERENCE_STATE ZN LIQUID * 1E5


TABLE_VALUES

\$ X(ZN)	X(AL)	HMR	DH
0.2	0.8	1568	DH
0.4	0.6	2430	DH
0.6	0.4	2508	DH
0.8	0.2	1723	DH

TABLE_END



Al-Zn 相图实验数据: 液相活度



Activity of a phase example

\$ Activity of liquid phase at 1000K

TABLE_HEAD

CREATE_NEW_EQUILIBRIUM @@,1

CHANGE_STATUS PHASE *=S

CHANGE_STATUS PHASE LIQUID=FIX 1

SET_CONDITION T=1000, P = P0, X(LIQUID,ZN) = @1

EXPERIMENT ACR(ZN)= @3 : @4

SET_REFERENCE_STATE AL LIQUID * 1E5

SET_REFERENCE_STATE ZN LIQUID * 1E5

TABLE_VALUES

\$ X(ZN)	X(AL)	ACR(ZN)	D	
0.2		0.8	0.35	DX1
0.4		0.6	0.55	DX1
0.6		0.4	0.7	DX1
0.8		0.2	0.83	DX1

TABLE_END



